

nanoCAD

Installation and Registration Guide

Nanosoft AS

TABLE OF CONTENTS

INTRODUCTION	1
INSTALLATION	2
INSTALLATION OF ADDITIONAL MODULES	6
REGISTRATION	7
Register or activate license file	7
Request license file online	9
Request license file by e-mail	11
Go to personal account on website	12
Save license request	13
Activate license file.....	13
License file location.....	14
NETWORK LICENSE ACTIVATION	15
Connect to License Server	15
Specify License Server	15
License Borrowing.....	16
How to Borrow License	16
About.....	17
NETWORK LICENSING	18
Run License Server	18
Request Network License	19
User Authentication	20
Confirm Registration Data	21
Send Registration Data to Licensing Server	21
Request license file by email	22
Respond from Licensing Service	23
Configure License Server	23
Remote connection to License Server.....	26
POSSIBLE PROBLEMS AND HOW TO FIX THEM	27
Get error when start setup.exe file	27
Installation Wizard does not accept serial number	27
Software does not run	27

Introduction

This instruction explains the process of installation of nanoCAD products.


nanoCAD consists of simple nanoCAD and Modules. Simple nanoCAD is a complete product, it includes base functionality. Modules include additional functionality that expands the program capabilities.

There are the following modules:

- Construction,
- Mechanica,
- Topoplan,
- 3D,
- Raster.


Each module is licensed independently of the others.

After installation of nanoCAD with all modules, there appear three desktop shortcuts. They allow to run the program in one of three configurations: Platform, Mechanica and Construction:




Installation

When the downloading process has finished, the Setup Wizard dialog box appears. You can also start installation by double clicking on the installation file with .exe file format:




Click *Next* to continue.

In the next window you should read the End-User License Agreement. To continue, check *I accept the terms in the License Agreement* box and click *Next* button:




nanoCAD Installation and Registration Guide

Enter your name, company and serial number. Serial number can be found in your personal account on website. If you cannot enter serial number now, uncheck *I have serial number* option and click *Next* to continue:



The screenshot shows the 'Customer Information' dialog box in the nanoCAD x64 23.0 Setup. The window title is 'nanoCAD x64 23.0 Setup'. The main heading is 'Customer Information' with the instruction 'Please enter your information.' and the nanoCAD logo. There are three input fields: 'User Name', 'Company', and 'Serial number'. The 'Serial number' field has a checked checkbox labeled 'I have serial number' and a 'Paste' button. The serial number field contains the text 'NC230AS-XXXXXXXXXXXX-XXXXX'. At the bottom, there are three buttons: '< Back', 'Next >', and 'Cancel'.


Choose the folder where the program will be installed. We recommend to not change the default folder:




The screenshot shows the 'Destination Folder' dialog box in the nanoCAD x64 23.0 Setup. The window title is 'nanoCAD x64 23.0 Setup'. The main heading is 'Destination Folder' with the instruction 'Click Next to install to the default folder or click Change to choose another' and the nanoCAD logo. Below the heading, it says 'Install nanoCAD x64 23.0 to:'. There is a text box containing the default path 'C:\Program Files\Nanosoft AS\nanoCAD x64 23.0\' and a 'Change...' button. At the bottom, there are three buttons: '< Back', 'Next >', and 'Cancel'.

nanoCAD Installation and Registration Guide

At the following step of the installation process you should choose *Mechanica* and *Construction* modules if you need to install them. **We recommend to install these modules only if you have licenses for them.** Other modules – *3D*, *Raster*, *Topoplan* – will be installed by default.




Associate .dwg (drawing), .dwt (drawing template), .dxf (drawing exchange format) and .dws (standards) files with nanoCAD:




Click the *Install* button to start the installation process:

nanoCAD Installation and Registration Guide



After the installation process, you will be prompted to run Registration Wizard and register nanoCAD.



Choose *Launch RegWizard* option to start Registration Wizard automatically. You can uncheck this option and start Registration Wizard later from *Start – nanoCAD – Registration Wizard* menu. Click *Finish*.

Installation of Additional Modules

nanoCAD is a multicomponent software, it includes base Platform and additional components:


- Construction;
- Mechanica;
- Topoplan;
- 3D;
- Raster.

You can refuse installation of Construction and Mechanica at the installation process, other modules will be installed automatically.

Add module

If you bought additional module, make sure that it is switched on in the program options.


- Open *Options* dialog;
- Find *Licensing – Modules* section;
- Select required components and click *OK*;
- Restart nanoCAD.



Registration


Run Registration Wizard after the installation of nanoCAD.

- If you need to activate the license or get serial number, choose *Register or activate license file* option.
- If you have received license file and need to activate it, choose *Manually activate license file* option.
- If you use network license and License Server is installed and runs, choose *Connect to License Server* option. Otherwise, close Registration Wizard: you should [install License Server](#) at first.




Register or activate license file

If you have serial number, enter it in the field and click *Next*. The *User Authentication* window will be opened. Otherwise choose *Get serial number* option. You will be redirected to www.nanocad.com website. Follow site instruction for getting serial number, then start Registration Wizard again to activate your license.




nanoCAD Installation and Registration Guide

In User Authentication window enter the following data: your name, your company's name, country and login (it coincides with email). Note that password is not required!



The 'User Authentication' dialog box features the nanoCAD logo on the left. The 'User information' section contains three input fields: 'Person' with the placeholder 'Your name', 'Company' with 'Company name', and 'Country' with a dropdown menu showing 'Your country'. Below this, the 'Authenticate on www.nanocad.com' section has a 'Login' field containing 'email@email.com' and a note that 'Password isn't required for authentication.' A blue link 'Register new user on www.nanocad.com' is positioned below the login field. At the bottom, there are four buttons: '< Back', 'Next >', 'Cancel', and 'Help'.

Check your information in *Confirm Registration Data* window. This information will be sent to Nanosoft AS company for getting the local license. Click *Next* if the data is correct or *Back* to change it.



The 'Confirm Registration Data' dialog box displays the nanoCAD logo on the left. A scrollable text area on the right shows the following registration details: CDKey: NC230AS-, Login: email@email.com, ID 1: 84A93E36C369 0A0027000010 00FF, ID 2: 329E901D, Customer: Your name, Company: Company name, Country: Your country, Build: 23.0.6147.4115, and RWB: 73. Below the scroll area, the text 'Click Next to choose the way of sending data' is displayed. At the bottom, there are four buttons: '< Back', 'Next >', 'Cancel', and 'Help'.

Click Yes:

nanoCAD Installation and Registration Guide

Registration Wizard




Attention!
Requested license will be attached to this computer. It is impossible to transfer a license to another computer.
Continue the license request?

Yes


No

Then *Send Registration Data to Licensing Server* window will be opened.

Request license file online



This option can be chosen on computers that have Internet connection. Registration Wizard connects with License Server through the Internet, gets the license, then saves it on computer and activates automatically.



Note. License files are located in the following folder by default: *C:\ProgramData\Nanosoft AS\RegWizard\Licenses*.

The result of an online license request may be:


- license file successfully received;
- license file request failed;
- failed connection to Licensing Server.

If the product was successfully activated, click *Next*, then *Finish*.


Congratulations! License file successfully received. Product is activated.

In the case if you don't have Internet connection or you get *failed connection* error, request license file in another way.

Request license file by e-mail




It is possible to get license file by e-mail. Choose this option in *Send Registration Data to Licensing Server* window of the Registration Wizard. Email will be generated automatically; you should send it. Please do not edit the message.



nanoCAD Installation and Registration Guide


You will get an email with license file. Save this file on your PC, then start Registration Wizard and choose *Manually activate license file* option.




Click *Finish*.

Go to personal account on website

Use this option to open your personal account on the website www.nanocad.com. Registration Wizard will be closed.




Save license request



It is possible to save license request in text file. You will be able to transfer this file to another computer and send to Licensing Server or Support Portal through the Internet. Registration Wizard will automatically generate *LicenseRequest.eml* file – this is text file including an important information for getting the license. Send this file to your support manager, then you will get the license file and further instructions.


Activate license file

If you received the license file, you should activate it. Save this file on computer. Start Registration Wizard, choose *Manually activate license file* option:



License file location

Click *Browse* to specify the location of the license file.



Click *Next*.

Congratulations! License file successfully received. Product is activated.


Network license activation

Network licensing requires a TCP/IP connection. Install License Server on one of computers in the local network. Install nanoCAD on every computer which will use it, then connect nanoCAD with License Server through the Registration Wizard by the name of Server PC or its IP address.

Network license provides installing nanoCAD on any number of PCs, but no more than the number of paid PCs will be able to start nanoCAD at the same time.


Connect to License Server

If Nanosoft License Server is installed in the local network, you should connect nanoCAD to it. Run Registration Wizard, choose *Connect to License Server* option and click *Next*:



Specify License Server

Enter the IP-address of computer where the License Server runs (for example, 192.168.0.1), or a NetBIOS-name of this computer (for example, CORPSRV). If you use irregular ports, enter the name of port and server name: <port>@<server_name> (for example, 270010@CORPSRV):



Click *Next*.

Congratulations! Product is activated.

License Borrowing


License borrowing allows to use nanoCAD outside the local network during a certain time. This option doesn't work by default, please connect Support Center support@nanocad.com for getting specific license file.

How to Borrow License

To borrow license from the License Sever:

- call the BORROWLICENSE command in the nanoCAD command line;
- Specify end borrowing date and click *OK*.


nanoCAD Installation and Registration Guide



At the end of the specified date the borrowed license will be returned to the License Server. To turn the license back to server earlier, connect nanoCAD to License Server and call RETURNLICENSE command.

About


You can find your license information in About dialog



Network Licensing


Download *License Server* from the website <https://nanocad.com/products/nanocad-platform/download/>. Network licensing in nanoCAD contains the set of utilities for installation, maintenance and control of network licenses:

- License Server Setup Wizard is an utility for installation and maintenance of network licenses. It installs, deletes, services the server part of the network license;
- Nanosoft AS License Server is a server part of network licensing; it includes the set of programs, utilities, services which control licenses and provide reports. You can find them at: C:\Program Files (x86)\CSoft AS\CSoftAS License Server



Run License Server


Start LicServSetupNanosoftAS.exe file:



The first option *Request license file* is the main one. Choose it when you start License Server at the first time and need to install it, when you need to activate the license, or get new license file for existing server. If you already have the license file, or you need to stop or delete License Server, choose the second option *Manage License Server*.


Request Network License

If you didn't get the license file yet, choose Request license file option. Enter serial number of your network license and click *Next*. You can find serial number in the personal account on website.



nanoCAD Installation and Registration Guide


If you don't have the serial number, use *Get serial number* option. Click *Next*: you will be redirected to nanocad.com website. License Server Setup Wizard will be closed. Please run License Server Setup again when the serial number is received.



The dialog box titled "Serial number" features a close button (X) in the top right corner. On the left side, there is a logo consisting of a blue square with a white 'n' and a white document icon with a blue ribbon seal. The main area contains two radio button options: "Enter serial number" (unselected) and "Get serial number" (selected). Below the "Get serial number" option, there is a text instruction: "Follow to site www.nanocad.com, register and get your serial number". At the bottom of the dialog, there are three buttons: "< Back", "Next >", and "Cancel".

User Authentication


Enter your data: User Name, Company Name, Login (is the same with your email). Note: password is not required.



The dialog box titled "User authentication" features a close button (X) in the top right corner. On the left side, there is a logo consisting of a blue square with a white 'n' and a white document icon with a blue ribbon seal. The main area is divided into two sections. The first section, "User information", contains two labels with corresponding text boxes: "User:" with "Your name" and "Company:" with "Your company". The second section, "Authenticate on www.nanocad.com", contains a "Login:" label with a text box containing "email@email.com". At the bottom of the dialog, there are three buttons: "< Back", "Next >", and "Cancel".

Confirm Registration Data


Check your data. If it is correct, click *Next*. Otherwise click *Back* to edit it.



Send Registration Data to Licensing Server


Choose one of the methods to get the license file.

If computer has Internet connection, choose *Request license file online* option and click *Next*.




Request license file by email

It is possible to get license file by e-mail. Choose this option in *Send Registration Data to Licensing Server* window of the License Server Setup.



Email will be generated automatically, you should send it. Please do not edit the message.




nanoCAD Installation and Registration Guide

It is possible to save a license request to text file. You will be able to transfer this file to another computer with Internet connection and send to Licensing Server or Support Portal. Program will automatically generate *LicenseRequest.eml* file – it is a text file with important information for getting the license. Send this file to your support manager, then you will get the license file and further instructions.


Respond from Licensing Service

If you request the license file online, License Server will receive it, save and activate automatically.




Configure License Server

After you have received the license file, you should configure License Server. Run License Server Setup Wizard, choose *Manage License Server* option:




Manage License Server window includes several options:




- Install or upgrade License Server. Use this option if the License Server is not installed yet. Specify the location of the license file, then click *Next*. Network license files are located in *C:\ProgramData\CSoft AS\LicServSetup\Licenses* folder by default:


nanoCAD Installation and Registration Guide



Then specify License Service and Vendor Daemon TCP ports. Use default ports or set specific ones. Click *Next*:



- Add License File to License Server. Use this option when License Server is installed and works and you need to update or upgrade the current license. Specify the license file location and click *Next*. Network license files are located in `C:\ProgramData\CSoft AS\LicServSetup\Licenses` folder by default.



The License file will be added to License Server. The Server will be restarted automatically.

Remote connection to License Server

There is a possibility to connect to remote License Server through the Internet. To do this, you need to forward the port of the License Server (standard port 27000), so that it is available for connection from the global network and has a public (permanent) IP address on the computer where the License Server is installed. In this case, you can connect to the License Server from any computer that has Internet access. To connect to the License Server configured for Internet connections, you will need to specify not only the external IP address in the Registration Wizard but also the port, using the @ symbol, for example, *27000@external_ip*.

Possible problems and how to fix them

You can read information about the most common problems below. If you cannot solve the problem, contact our Support Center: support@nanocad.com.

Get error when start setup.exe file

1. Make sure the installation file is downloaded completely and correctly.
2. Make sure the computer meets the system requirements for the software.
3. Try to install nanoCAD on another computer.
4. Try to localize the problem and send the message to Support Center.

Installation Wizard does not accept serial number

1. Make sure that you enter the serial number for the software you are installing. For example, NC230AS-xxxxxxxxxxxx-xxxxx for nanoCAD 22, it is another product. NanoCAD 23.0 does not work on this license.
2. Make sure that you entered all the symbols correctly. Serial number doesn't include O letter, only 0 digit.
3. Make sure the inserted serial number doesn't include non-printable characters (space, tab, etc.).
4. Contact Support Center. Don't forget to specify the name and version of the software and the serial number you're trying to activate.

Software does not run

1. Make sure the computer meets the system requirements for the software.
2. Make sure that the installed files are not damaged. For example, if the computer is infected with virus, then antivirus software can move nanoCAD's files to the quarantine.
3. Contact Support Center. Try to explain the problem in detail, don't forget to specify the version of nanoCAD.